


Case study for EPSDock

1、Experimental Environment:

Windows 11 and Ubuntu 18.04

Install MGL Tools in the Ubuntu 18.04 environment:

Download link: <https://ccsb.scripps.edu/mgltools/downloads/>



2、Download PDB file for RNA target (use PDB ID: 1EHT as an example).

Structure Summary | Structure | Annotations | Experiment | Sequence | Genome | Versions

← NMR Ensemble →

1EHT | pdb_00001eht¹

THEOPHYLLINE-BINDING RNA IN COMPLEX WITH THEOPHYLLINE, NMR, 10 STRUCTURES

PDB DOI: <https://doi.org/10.2210/pdb1EHT/pdb> NAKB: 1EHT

Classification: RNA
Mutation(s): No

Deposited: 1997-03-20 Released: 1997-12-24
Deposition Author(s): Zimmermann, G.R., Pardi, A.

Experimental Data Snapshot

Method: SOLUTION NMR
Conformers Calculated: 50
Conformers Submitted: 10
Selection Criteria: LOWEST TOTAL ENERGY

wwPDB Validation


Metric Clashscore RNA backbone Value 12 0.19

Percentile relative to all structures
Percentile relative to all NMR structures

Explore in 3D: Structure | Sequence Annotations | Validation Report | Ligand Interaction (TEP)

3、 Prepare the RNA receptor PDB file.

In Windows, use PyMOL to extract the receptor macromolecule (1eht_r) and the ligand small molecule (1eht_l) from the 1eht co-crystallized compound, remove water molecules from the environment, and save the files in .pdb format as 1eht_r.pdb and 1eht_l.pdb. Open the receptor PDB file using the ADT (AutoDock Tools) software.



4、 Use ADT to preprocess the RNA receptor file

1) Preparing receptor and ligand files using AutoDock Tools (ADT) software:

Go to **File** → **Preferences** → **Set** → **Startup Directory** → Set it to the folder containing the receptor and ligand files → Click **Make Default** → Close the window.


2) Go to **File** → **Preferences** → **Set** → **Startup Directory** → Set it to the folder containing the receptor and ligand files → Click **Make Default** → Close the window.

3) Go to **File** → **Read Molecule** → Select the receptor macromolecule .pdb file → Click **Open**.

4) Go to **Edit** → **Hydrogens** → **Add** → Click **OK**.


5) Go to **Edit** → **Charges** → **Compute Gasteiger** → Click **OK**.

6) Navigate to **Edit** → **Charges** → **Compute Gasteiger** → Click **OK**




5、 Use Grid to prepare the RNA receptor and ligand file


1) Go to **Grid** → **Macromolecule** → **Choose** → Select the receptor molecule → **Select Molecule** → Click **OK** → Save to the working folder → **Save**.




2) Edit—>Delete All Molecules—>CONTINUE;




3) Go to **File** → **Read Molecule** → Select the ligand molecule **1eht_l.pdb** → Click **Open**.




4) Edit—>Hydrogens—>Add—>OK;





5) Go to **Edit** → **Charges** → **Compute Gasteiger** → Click **OK**



6) Go to **Ligand** → **Input** → **Choose** → Select the ligand molecule → **Select Molecule for AutoDock4** → Click **OK**




7) Ligand—>Torsion Tree—>Detect Root;




Ligand—>Torsion Tree—>Show Root Expansion;

- 9) Ligand—>Torsion Tree—>ShowHide Root Marker;
- 10) Ligand—>Torsion Tree—>Choose Torsions—>Done;




11)




Ligand—>Output—>Save as PDBQT;


12) Edit—>Delete All Molecules—>CONTINUE;




13) Go to **Grid** → **Macromolecule** → **Open** → Select the receptor .pdbqt file → Click **Open** → **Yes** → **OK** → **OK** → **OK**.




14) Go to Grid → Set Map Types → Open Ligand → Select the ligand molecule .pdbqt file → Click Open.





15) In the DejaVu GUI, navigate to the root object → Select the ligand molecule → Open Preferences → Uncheck the box next to "Transf. Root Only" → Right-click the ligand molecule → Move the ligand molecule outside of the receptor molecule → Open Preferences again → Check the box next to "Transf. Root Only".




16) Go to Grid → Grid Box → Adjust the box size to enclose the entire protein → File → Close Saving Current.



17) Navigate to Grid → Grid Box → Adjust the box size to ensure it encloses the entire protein → Go to File → Select Close Saving Current.




18) Go to Grid → Output → Save GPF → Save the .gpf file



19) Navigate to the folder containing the protein receptor and ligand files using the cd command, then execute the following command:

```
// autogrid4 -p 1eht.gpf
```



20) After the Grid calculation completes, proceed to:

Docking → **Macromolecule** → **Set Rigid Filename** → Select the RNA molecule (to set the RNA molecule as rigid)

6、Perform docking

1) After the Grid process is completed, go to **Docking** → **Macromolecule** → **Set Rigid Filename** → Select the RNA molecule (to set the RNA molecule as rigid)


2) **Docking** → **Ligand** → **Open** → Select the ligand → **Accept**.

3) **Docking** → **Ligand** → **Choose** → Select 1eht_l_2 → **Select Ligand** → **Accept**.

4) **Docking** → **Search Parameters** → **Genetic Algorithm (GA)** → **Accept**

5) **Docking** → **Docking Parameters** → **Accept**;

6) Go to **Docking** → **Output** → **Lamarckian GA** → Save the file in .dpf format



- 7) Modify the run parameters of the search algorithm in 1eht.dpf,
Original search algorithm parameter settings:

```
ga_pop_size 150           # number of individuals in population
ga_num_evals 2500000      # maximum number of energy evaluations
ga_num_generations 27000  # maximum number of generations
ga_elitism 1              # number of top individuals to survive to next generation
ga_mutation_rate 0.02     # rate of gene mutation
ga_crossover_rate 0.8     # rate of crossover
ga_window_size 10         #
ga_cauchy_alpha 0.0       # Alpha parameter of Cauchy distribution
ga_cauchy_beta 1.0        # Beta parameter Cauchy distribution
set_ga                   # set the above parameters for GA or LGA
sw_max_its 300            # iterations of Solis & Wets local search
sw_max_succ 4             # consecutive successes before changing rho
sw_max_fail 4             # consecutive failures before changing rho
sw_rho 1.0               # size of local search space to sample
sw_lb_rho 0.01           # lower bound on rho
ls_search_freq 0.06       # probability of performing local search on individual
set_psw1                 # set the above pseudo-Solis & Wets parameters
unbound_model bound       # state of unbound ligand
ga_run 10                 # do this many hybrid GA-LS runs
analysis                  # perform a ranked cluster analysis
```


8) Change to the parameters for the EPSDock search algorithm

```
pso_c1 2.05          # the First Confidence Coefficient
pso_c2 2.05          # the Second Confidence Coefficient
pso_k 50             # Max number of particles informed by a given one
pso_swarm_moves 2500000 # total swarm Moves
pso_size 50          #swarm size
pso_n_exec 100       #Number of requested PSO runs or the total running times
sw_max_its 50        # iterations of Solis & Wets local search
sw_max_succ 2        # consecutive successes before changing rho
sw_max_fail 2        # consecutive failures before changing rho
sw_rho 1.0           # size of local search space to sample
sw_lb_rho 0.01       # lower bound on rhon
ls_search_freq 0.06  # probability of performing local search on individual
set_psw1             # set the above pseudo-Solis & Wets parameters
unbound_model bound  # state of unbound ligand
do_cpso              # perform a ranked cluster analysis
```

9) Navigate to the directory containing the receptor and ligand files, then execute the following command to run the docking experiment:

```
//epsdock -p 1eht.dpf
```

10) Extracting docking results:

Open the docking log file 1eht.dlg to view the results, including:

The lowest energy conformation of the docked structure.

The docking coordinates of the ligand.

```
USER  RMSD from reference structure    = 2.689 A
USER
USER  Estimated Free Energy of Binding  = -5.78 kcal/mol [(1)+(2)+(3)-(4)]
USER  Estimated Inhibition Constant, Ki = 58.27 uM (micromolar) [Temperature = 298.15 K]
USER
USER  (1) Final Intermolecular Energy   = -5.78 kcal/mol
USER    vdW + Hbond + desolv Energy     = -5.68 kcal/mol
USER    Electrostatic Energy           = -0.09 kcal/mol
USER  (2) Final Total Internal Energy   = +0.00 kcal/mol
USER  (3) Torsional Free Energy         = +0.00 kcal/mol
USER  (4) Unbound System's Energy [(2)] = +0.00 kcal/mol
USER
```


As a reference, EPSDock Experimental Setup:

Software Environment:

OS: Ubuntu Desktop 18.04 LTS

Docking Tools: EPSDock, FIPSDock, AutoDock, AutoDock Vina, rDock, Glide

Visualization/Analysis: PyMOL, ADT (AutoDock Tools 4.6)

Hardware Environment:

CPU: Intel i9-9900 @ 3.1 GHz

GPU: NVIDIA GTX 1060

(Note: This configuration assumes all software is properly installed and configured for GPU acceleration where applicable.)